


Leica Geosystems Licence Activation Guide


Licence Activation for CS10/CS15





Dear valued customer...

Thank you for purchasing a licence for our product. The following instructions will guide you through the licence activation process.


-  Please register your product at myWorld.leica-geosystems.com, our internet platform for our customers. myWorld provides 24/7 access to all information you require to actively manage your equipment. Here, detailed information on individual products and their service history can be found. The information also aids in maintaining the product value while at the same time enabling maximum efficiency and productivity.

Activate licence

-  The procedure is valid for any licence key.

Step	Description		
	You can download licence keys from myWorld. Refer to "Download licence".		
	To upload a licence key, store the licence key file (for example L_2500123.key) in the \SYSTEM directory of the data storage device. Insert the data storage device into your product.		
1.	Turn on the product.		
2.	Go to User\Tools & other utilities\Load licence keys .		
3.	<table border="0"><tr><td>To type in a licence key: Select Load key: Enter manually Key:Type in the licence key.</td><td>To upload a licence key: Select Load key: Upload key from file Device: Select your data storage device in use.</td></tr></table> <p>Click OK. The licence is activated and can be used.</p>	To type in a licence key: Select Load key: Enter manually Key: Type in the licence key.	To upload a licence key: Select Load key: Upload key from file Device: Select your data storage device in use.
To type in a licence key: Select Load key: Enter manually Key: Type in the licence key.	To upload a licence key: Select Load key: Upload key from file Device: Select your data storage device in use.		
	If an application licence was activated but the application is not loaded on the product refer to "Download application" and "Upload application".		
	If a software maintenance licence was activated refer to "Update software" to update the software on the product.		


Download licence

-  The procedure is valid for any licence key.


Step	Description
1.	Go to www.myworld.leica-geosystems.com and log in.
2.	Go to myProducts and select your product.

- when it has to be **right**

Leica
Geosystems

Step	Description
	If your product is not in the list, click Add Product .
3.	On the Overview tab, click Download keys . In the next window, click Save and select a directory to save the file to. Click Save . Copy the *.key file to the \SYSTEM directory of the data storage device.


Download application

Step	Description
1.	Go to www.myworld.leica-geosystems.com and log in.
2.	Go to myProducts and select your product.
	If your product is not in the list, click Add Product .
3.	Click the Software tab and download the applications to your computer. The zip file contains all applications.
4.	Unzip the file and store the required application files in the \SYSTEM directory of the data storage device.

Upload application

Step	Description
1.	Insert the data storage device into your product and turn on the product.
2.	Go to User\Tools & other utilities\Load firmware & Apps .
3.	Select: Object to transfer: Apps From: Select your data storage device in use. App: Select the application to upload.
4.	Click OK . The application software is uploaded to your product.

Update software

Step	Description
1.	Connect your product to the computer.
2.	Go to www.myworld.leica-geosystems.com and log in.
3.	Go to myProducts and select your product.
	If your product is not in the list, click Add Product .
4.	On the Software tab, look in the section Automatic Online Software Update .
5.	Click Start Update .

In case activation fails...

In case the licence activation fails:

- contact your local Leica Geosystems agency.

OR

- create new support requests on myWorld.leica-geosystems.com that will be answered by your local Leica Geosystems Support Team.

- when it has to be **right**

Leica
Geosystems